




Installing New Software Version using USB

- ▶ Pertama-tama Download File update nya pada link berikut:
- ▶ <https://6kav2.updatemyunit.net/>
- ▶ Lalu pilih link server Singapore seperti yang ditandai di bawah:




Then press : Software Upgrade

With Legacy Software Version, Setup Unit : HOME -> System Settings -> Upgrade Parameters -> Server Name with : 6kav2.updatemyunit.net
Then press : Exit -> Expert Tools -> Upgrade -> Software Upgrade


Download latest Fiber Optics Software Application			
 Base6kav2-19434-Win32.exe [502.773 M]	Release Notes	Year:2019 Week:43 Day:4 [Thu 24 Oct 2019]	"Boot" = 9.04 04/11/2019 "Linux Kernel" = 8.86 04/16/2019 "File System" = 9.10 10/08/2019 "Instrument Setup" = 18.50 10/24/2019 "Microscope" = 18.50 10/24/2019 "Fiber Optics" = 18.50 10/24/2019
Download Latest Combo (Fiber Optics and BERT) Software Application			
 Base6kav2-19434-Bert-26.3.3-Win32.exe [1461.588 M]		Year:2019 Week:43 Day:4 [Thu 24 Oct 2019]	"Boot" = 9.04 04/11/2019 "Linux Kernel" = 8.86 04/16/2019 "File System" = 9.10 10/08/2019 "Instrument Setup" = 18.50 10/24/2019 "Microscope" = 18.50 10/24/2019 "Fiber Optics" = 18.50 10/24/2019 "BERT" = 26.3.3 08/16/2019
Download Latest Fiber Characterization Software Application			
 Base6kav2-18205-FC-Win32.exe [477.519 M]	Release Notes	Year:2018 Week:20 Day:5 [Fri 18 May 2018]	"Boot" = 7.18 04/05/2018 "Linux Kernel" = 8.76 04/05/2018 "File System" = 7.22 05/17/2018 "Instrument Setup" = 16.70 05/18/2018 "Microscope" = 16.70 05/18/2018 "Fiber Optics" = 16.70 05/18/2018

- ▶ Tunggu sampai proses download selesai
- ▶ Kamu haru menggunakan USB dengan minimal kapasitas 128 Mb
- ▶ Sebelum proses install kamu haru mem-format atau mengosongkan USB terlebih dahulu
- ▶ Setelah download selesai, copy file ke dalam USB yang akan digunakan

- ▶ Lalu extract file tersebut ke dalam USB yang akan digunakan



► Tunggu sampai proses extract selesai



- ▶ Setelah proses extract file selesai, cabut usb dengan cara yang proper dari laptop anda
- ▶ Lalu masukkan USB ke dalam MTS-6000 yang akan di update
- ▶ Pada home page tekan **Connectivity** icon



- ▶ Tekan **Upgrade** icon



- ▶ Tekan Software Upgrade -> Upgrade from USB
 lalu The message Are you sure? Muncul
- ▶ Klik **Confirm**

- ▶ List dari software version available pada USB akan muncul seperti gambar di bawah



Software Version Information			Upgrade Version Information		
Microscope	1.50	22/03/2015	Microscope	3.50	↑ 22/04/2015
Instrument Setup	2.50	22/03/2015	Instrument Setup	5.50	↑ 22/04/2015
Fiber Optics	2.50	22/03/2015	Fiber Optics	3.50	↑ 22/04/2015
Boot	2.50	22/03/2015	Boot 27/04	3.50	↑ 24/04/2015
Linux Kernel	2.50	22/03/2015	Linux Kernel	3.50	↑ 22/04/2015
File System	2.50	22/03/2015	File System	5.00	↑ 24/03/2015

Confirm this Choice

Exit

- ▶ Confirm this choice
- ▶ Tunggu sampai seluruh proses selesai